

# ADAS Subroutine etred9inv

FUNCTION ETRED9INV( KTYPE , EIJ , TR , B , C )

C-----  
C  
C \*\*\*\*\* FORTRAN 77 FUNCTION: ETRED9INV \*\*\*\*\*  
C  
C PURPOSE: TO CALCULATE THE ELECTRON ENERGY FROM THE REDUCED ENERGY  
C FOR EIGHT TYPES OF TRANSITION  
C  
C CALLING PROGRAM: ADAS108  
C  
C FUNCTION:  
C  
C INPUT: (R\*8) EIJ = TRANSITION ENERGY (Eij)  
C (R\*8) TR = REDUCED ENERGY  
C (R\*8) B = BURGESS SCALING PARAMETER - B  
C (R\*8) C = BURGESS SCALING PARAMETER - C  
C (R\*8) TL =  $E_j/E_{ij}$   
C (I\*4) KTYPE = TRANSITION TYPE  
C 1 ELECTRIC DIPOLE - EXP THRESHOLD  
C 2 NON ELECTRIC DIPOLE - EXP THRESHOLD  
C 3 SPIN CHANGE - EXP THRESHOLD  
C 4 OTHER - EXP THRESHOLD  
C 5 ELECTRIC DIPOLE - POWER THRESHOLD  
C 6 NON ELECTRIC DIPOLE - POWER THRESHOLD  
C 7 SPIN CHANGE - POWER THRESHOLD  
C 8 OTHER - POWER THRESHOLD  
C  
C OUTPUT: (R\*8) ETRED9INV= ELECTRON ENERGY  
C  
C (I\*4) IASYMC = ASYMPTOTIC CLASSIFICATION TYPE  
C (I\*4) ITHRSC = THRESHOLD CLASSIFICATION TYPE  
C (R\*8) E0 = SWITCHING ENERGY  
C  
C ROUTINES: NONE  
C  
C DATE: 25/05/99 VERSION 1.1  
C AUTHOR: HUGH SUMMERS, UNIVERSITY OF STRATHCLYDE  
C-----

INTEGER KTYPE  
REAL\*8 B, C, EIJ, TR